



98-365^{Q&As}

Windows Server Administration Fundamentals

Pass Microsoft 98-365 Exam with 100% Guarantee

Free Download Real Questions & Answers **PDF** and **VCE** file from:

<https://www.geekcert.com/98-365.html>

100% Passing Guarantee
100% Money Back Assurance

Following Questions and Answers are all new published by Microsoft
Official Exam Center

- ⚙ **Instant Download** After Purchase
- ⚙ **100% Money Back** Guarantee
- ⚙ **365 Days** Free Update
- ⚙ **800,000+** Satisfied Customers





QUESTION 1

You purchase a device from an online retailer and install it in a computer running Windows Server 2016. You are having intermittent problems and want to look for an updated driver.

You attempt to update the driver through Device Manager, but the utility is unable to find an updated driver.

Where should you look next?

- A. Microsoft Windows Download Center
- B. online retailer technical support
- C. Windows installation software disk
- D. the device manufacturer website

Correct Answer: A

QUESTION 2

To change the boot device order of a computer, you should use:

- A. Device Manager.
- B. Disk Management.
- C. BIOS settings.
- D. Computer Policy.

Correct Answer: C

Example: Change the Boot Order in BIOS

Turn on or restart your computer and watch for a message during the POST about a particular key, usually Del or F2, that you'll need to press to ...enter SETUP. Press this key as soon as you see the message.

QUESTION 3

You need to find a list of specific events. What should you do?

- A. Export the events to a .doc file.
- B. Clear the log by saving it.
- C. Filter by creating a custom view.
- D. Use the Search menu option.

Correct Answer: C



Quickly Filter Event Logs in Windows Server 2016

The Event Viewer automatically creates several filtered views of the event logs. Filtered views are listed under the Custom Views node.

QUESTION 4

What partitioning style supports up to 18 EB and 128 partitions?

- A. MBR
- B. GPT
- C. Dynamic
- D. Basic

Correct Answer: B

GUID Partition Table (GPT) is a newer partitioning style that supports up to 18 exabytes (EB) or 18 billion gigabytes and can store up to 128 partitions on each disk. This style is also more faults tolerant because it stores a duplicate set of partition tables.

QUESTION 5

What is the default path for the print spool folder?

- A. C:\Windows\System32\Spool\Printers
- B. C:\Windows\System\Spool32\Printers
- C. C:\Users\Microsoft\Spool\Printers
- D. C:\Windows\System32\Spool\Printer

Correct Answer: A

When the print device is available, the spooler retrieves the next print job and sends it to the print device.

By default, the spool folder is located at C:\Windows\System32\Spool\Printers.

If you have a server that handles a large number of print jobs or several large print jobs, make sure the drive where the spool folder is has sufficient disk space.

[Latest 98-365 Dumps](#)

[98-365 Practice Test](#)

[98-365 Braindumps](#)