



# NCP-MCI-5.20<sup>Q&As</sup>

Nutanix Certified Professional - Multi cloud Infrastructure (NCP-5.20)





## Pass Nutanix NCP-MCI-5.20 Exam with 100% Guarantee

Free Download Real Questions & Answers **PDF** and **VCE** file from:

<https://www.geekcert.com/ncp-mci-5-20.html>

100% Passing Guarantee  
100% Money Back Assurance

Following Questions and Answers are all new published by Nutanix Official Exam Center


-  **Instant Download** After Purchase
-  **100% Money Back** Guarantee
-  **365 Days** Free Update
-  **800,000+** Satisfied Customers





### QUESTION 1

A two-node ROBO cluster is configured with a witness VM.



What happens when Node A goes down?

- A. The- cluster becomes unavailable and goes into read-only mode.
- B. All operations and services on the Node B are shut down and go into a waiting state.
- C. The cluster is unaffected and no administrator intervention is required.
- D. Node B sends a leadership request to the Witness VM and goes into single-node mode.

Correct Answer: D

### QUESTION 2

An administrator is trying to create an additional account on the Nutanix cluster in Prism Element but is unable to create new users.

- A. The OpenLDAP server was temporarily down for maintenance.
- B. The cluster has reached the minimum number of accounts.
- C. The administrator's account is assigned a Cluster Admin role.
- D. The connection to Active Directory server is disconnected.

Correct Answer: C



Reference: <https://next.nutanix.com/prism-infrastructure-management-26/user-management-and-ldap-s-setup-in-prism-element-and-prism-central-37338?postid=50119>

---

### QUESTION 3

Which feature must be enabled in order to ensure that VMs are restarted on other hosts in the event of a host failure?

- A. High Availability
- B. VM Snapshots
- C. Network Segmentation
- D. Live Migration

Correct Answer: A

---

### QUESTION 4

The administrator wants a container to be displayed and limited to 1TB in the hypervisor. What advanced container setting must the administrator set?

- A. Advertised Capacity
- B. Reserved Capacity
- C. Advertised Quota
- D. Reserved Quota

Correct Answer: A

---

### QUESTION 5

What command places a host in maintenance mode in AHV?

- A. `acli maintenance_mode.host host_id`
- B. `acli host.enter_maintenance_mode host_id`
- C. `ncli maintenance_mode host=host_id`
- D. `ncli host maintenance host_id`

Correct Answer: B

---



VCE & PDF

GeekCert.com

<https://www.geekcert.com/ncp-mci-5-20.html>

2024 Latest geekcert NCP-MCI-5.20 PDF and VCE dumps Download

---

[Latest NCP-MCI-5.20 Dumps](#)

[NCP-MCI-5.20 VCE Dumps](#)

[NCP-MCI-5.20 Exam Questions](#)